

---

# PI/Dwights PLUS<sup>®</sup> on CD

*Release Notes*

*April 2006—Version 1.7*



**The Source** for Critical Information and Insight™

© Copyright 2006, IHS Inc. and its affiliated and subsidiary companies, all rights reserved.

This documentation and the PI/Dwights PLUS<sup>®</sup> on CD software are not to be copied, reproduced, translated or transferred to any electronic medium or machine-readable format, except in the manner described in this documentation.

PI/Dwights PLUS is a registered trademark of IHS Inc. and its affiliated and subsidiary companies.

Because of the nature of this material, numerous hardware and software products are mentioned by their trade names in this publication. In most, if not all cases, these designations are claimed as trademarks by the respective owners. It is not the publisher's intent to use any of these names generically and the reader is cautioned to investigate all claimed trademark rights before using any of these names other than to refer to the product described.

Product names are registered trademarks of their respective companies. Mention of these products is for informational purposes and constitutes neither an endorsement nor a recommendation. IHS Inc. assumes no responsibility with regard to the selection, performance, or use of these products.

IHS Inc.  
15 Inverness Way East  
Englewood, CO 80112  
303-736-3000

## Enhancements

The following are enhancements to PI/Dwights PLUS on CD version 1.7.

### IHS Latitude/Longitudes

PI/Dwights PLUS on CD now uses IHS L&Ls for its map display and lat/long searches. The IHS L&Ls are updated daily—a significant improvement to the previous monthly updated L&Ls, providing more up-to-date map data.

### New Base Map Grid

The map now displays with the new IHS Land Grid, which is synched to the IHS L&Ls.

### Production Reports and Production Excel Workbook Export

Production reports and Production Excel Workbook export now double-map liquid gravity to look first in oil and then in condensate.

**Note:** This does not occur with one-line exports.

### New IHS Home Page

The IHS Energy Home Page command on the Help menu now takes you to the new IHS Energy Home Page.

## Bug Fixes

The following are bug fixes to PI/Dwights PLUS on CD version 1.7.

### 298 Production Export

The 298 production export now properly shows Carter locations on recently added producers.

### 297 Well Export

The ET record of the 297 export now correctly displays the source of tops data (1=Drillers; 2=Samples; 3=Log Top).

### Well Scout Ticket

Extra data displaying by the reference Elevation on the Well Scout Ticket has been removed.

In the DST portion of the Well Scout Ticket, the condensate ratio label is no longer overwriting the condensate ratio value.

## Upgrading to Version 1.7

**Note:** Installation of the PI/Dwights PLUS on CD software on your server and/or workstation is necessary to take advantage of the listed enhancements and modifications. This will not require you to uninstall your current release of software or reinstall your profile.

### Stand-alone Installation Instructions

1. On the taskbar, click the **Start** button, and then click **Run**.
2. In the Run dialog box, click **Browse**.
3. In the Browse dialog box, click the **Look In** drop-down list and select the appropriate CD-ROM drive.
4. Select (highlight) the Setup.exe and click **Open**.
5. Click **OK** on the Run dialog box.
6. In the Welcome screen, click **Next**.
7. In the Choose Destination Location screen, click **Next** to accept the default destination folder.  
**Note:** The default setting of C:\Program Files\IHS Energy\CD is highly recommended.
8. Click **Next** to accept the data path.  
**Note:** If the default path is not correct, click **Browse** and select the appropriate CD-ROM drive.
9. The Start Installation screen displays. Click **Next**.
10. The application will ask if you want to create a shortcut. Click **Yes** or **No**.
11. The Installation Complete screen displays. Click **Finish**.

### Network Installation Instructions

From the Installation CD-ROM, run netsetup.exe.

When prompted, select the drive or UNC where you want to install the network software.

**Note:** It is highly recommended to use the default directory, IHS Energy\CD to simplify installation and assist in support-related issues.

#### Netsetup.exe installs the following files:

Directory Structure	Files
<a href="#">\IHS</a> Energy\CD\	
	Install.log (Installation log)
	Profile.ini (license path)
	Setup.exe (client setup)
	Silent.exe (client setup)
	Unwise.exe (uninstall application)

<a href="#">\IHS Energy\CD\Profile\</a>	
	*.dat (license file)
	*.rtf (license document)
	Regions.ini (data regions path file)

## Install Workstation Software

The Setup.exe will allow the user to set the path on their workstation.

***Do not use the setup.exe contained on the Installation CD-ROM.***

The silent.exe automatically sets the path on the workstation to default.

The default setting is C:\Program Files\IHS Energy\CD.

To install the software using the setup.exe or silent.exe file:

Use [\IHS Energy\CD\setup.exe](#)

OR

silent.exe that were installed on the network server.

Either installation will set the workstation settings to read both the \*.dat (license file) and the regions.ini (data paths) files from the network. It is highly recommended to use the default settings to reduce support-related questions.

IHS Inc.  
 Client Support  
 800-468-3381  
 e-mail: [productcallcenter@ihsenergy.com](mailto:productcallcenter@ihsenergy.com)